

ETCD

2026.10.14 00:36:53

FAQ

语言:	i2	语言:	0
语言:	zh_CN	语言:	0.00 %
语言:	zh_CN	语言:	2026/10/08 16:25:03

400

400 Bad Request authentication is not enabled etcd

语言 (语言)

语言 (语言)

```
etcd[1010001712] ETCD Client error: `POST http://192.168.0.106:26352/v3/auth/authenticate` resulted in a `400 Bad Request` response: {"error":"etcdserver: authentication is not enabled","code":9,"message":"etcdserver: authentication is not enabled"}
```

语言 (语言)

```
etcd[etcd@root]
语言
语言/usr/info2soft/etcd/scripts/etcd_init.sh /usr/info2soft
语言
[root@localhost ~]# /usr/info2soft/etcd/scripts/etcd_init.sh /usr/info2soft
i2etcd started.
Add role, rolename: root
Add user, username: root
Password of root:
Type password of root again for confirmation:
User root created
Grant-role root to user root
Enable authentication
Authentication Enabled
The list of users can be viewed with the command: etcdctl user list
--user=root

语言
语言
/usr/info2soft/etcd/bin/etcdctl --endpoints 10.1.17.62:26352 user add root

/usr/info2soft/etcd/bin/etcdctl --endpoints 10.1.17.62:26352 auth enable
语言
/usr/info2soft/etcd/bin/etcdctl --endpoints 10.1.17.62:26352 user grant-role
root root

语言
[root@localhost ~]# /usr/info2soft/etcd/bin/etcdctl --endpoints
10.1.17.62:26352 user add root
Password of root:
Type password of root again for confirmation:
User root created
[root@localhost ~]# /usr/info2soft/etcd/bin/etcdctl --endpoints
10.1.17.62:26352 auth enable
{"level":"warn","ts":"2025-04-23T09:20:13.313566+0800","logger":"etcd-client","caller":"v3@v3.5.15/retry_interceptor.go:63","msg":"retrying
of unary invoker
failed","target":"etcd-endpoints://0xc000406000/10.1.17.62:26352","attempt":0,"error":"rpc
error: code = FailedPrecondition desc = etcdserver: root user does not have
root role"}
{"level":"warn","ts":"2025-04-23T09:20:13.314663+0800","logger":"etcd-client","caller":"v3@v3.5.15/retry_interceptor.go:63","msg":"retrying
of unary invoker
failed","target":"etcd-endpoints://0xc000406000/10.1.17.62:26352","attempt":0,"error":"rpc
error: code = FailedPrecondition desc = etcdserver: role name already exists"}
Error: etcdserver: role name already exists
[root@localhost ~]# /usr/info2soft/etcd/bin/etcdctl --endpoints
10.1.17.62:26352 user grant-role root root
Role root is granted to user root
[root@localhost ~]# /usr/info2soft/etcd/bin/etcdctl --endpoints
10.1.17.62:26352 auth enable
Authentication Enabled

语言
```