linux□□□□□□□□□□

2024.11.14 14:47:17

□□:	i2□□□□□□ FAQ	□□□□:	0
□□:	□□(□□)	□□:	0.00 %
□□:	zh_CN	□□□□:	□ 2023/08/25 17:16:43

□□□

-12

□□ *(□□)*

□□□□:□□□□□□□
□□:□□□□□□□□
□□:□□□□□□□□
□□□□:□□
□□□□□□□□:□□□

Linux□□□□□
Linux□□□□□
-0 is: Success □□

-1 is: Operation not permitted □□□□□□□

-2 is: No such file or directory □□□□□□□□

-3 is: No such process □□□□□

-4 is: Interrupted system call □□□□□□

-5 is: Input/output error □□□□□□

-6 is: No such device or address □□□□□□□□

-7 is: Argument list too long □□□□

-8 is: Exec format error □□□□□□

-9 is: Bad file descriptor □□□□□□□□

-10 is: No child processes □□□□□□

-11 is: Resource temporarily unavailable □□□□□□□

-12 is: Cannot allocate memory □□□□□□

-13 is: Permission denied □□□□

-14 is: Bad address □□□□

-15 is: Block device required □□□□□

-16 is: Device or resource busy □□□□□□

-17 is: File exists □□□□□

-18 is: Invalid cross-device link □□□□□□□□□

-19 is: No such device □□□□□

-20 is: Not a directory □□□□□□

-21 is: Is a directory □□□□□

-22 is: Invalid argument □□□□

-23 is: Too many open files in system □□□□□□□□

-24 is: Too many open files □□□□□□

-25 is: Inappropriate ioctl for device □□□□□□□□

-26 is: Text file busy □□□□□

-27 is: File too large □□□□

-28 is: No space left on device □□□□□□□□□□□□

-29 is: Illegal seek □□□□seek□□

-30 is: Read-only file system □□□□□□

-31 is: Too many links □□□□

-32 is: Broken pipe □□□□

-33 is: Numerical argument out of domain □□□□□□□□

-34 is: Numerical result out of range □□□□□□□□□

-35 is: Resource deadlock avoided □□□□

-36 is: File name too long 文件名过长

-37 is: No locks available 无可用锁资源

-38 is: Function not implemented 功能未实现

-39 is: Directory not empty 目录非空

-40 is: Too many levels of symbolic links 太多符号链接层

-41 is: Unknown error 41 41未知错误

-42 is: No message of desired type 没有所需类型的消息

-43 is: Identifier removed 标识符被删除

-44 is: Channel number out of range 通道数

-45 is: Level 2 not synchronized

-46 is: Level 3 halted

-47 is: Level 3 reset

-48 is: Link number out of range

-49 is: Protocol driver not attached

-50 is: No CSI structure available

-51 is: Level 2 halted

-52 is: Invalid exchange

-53 is: Invalid request descriptor

-54 is: Exchange full

-55 is: No anode

-56 is: Invalid request code

-57 is: Invalid slot

-58 is: Unknown error 58

-59 is: Bad font file format

-60 is: Device not a stream

-61 is: No data available

-62 is: Timer expired

-63 is: Out of streams resources

-64 is: Machine is not on the network

-65 is: Package not installed

-66 is: Object is remote

-67 is: Link has been severed

-68 is: Advertise error

-69 is: Srmount error

-70 is: Communication error on send

-71 is: Protocol error

-72 is: Multihop attempted

-73 is: RFS specific error

-74 is: Bad message

-75 is: Value too large for defined data type

-76 is: Name not unique on network

-77 is: File descriptor in bad state

-78 is: Remote address changed

-79 is: Can not access a needed shared library

-80 is: Accessing a corrupted shared library

-81 is: .lib secion in a.out corrupted

-82 is: Attempting to link in too many shared libraries

-83 is: Cannot exec a shared library directly

-84 is: Invalid or incomplete multibyte or wide character

-85 is: Interrupted system call should be restarted

-86 is: Streams pipe error

-87 is: Too many users

-88 is: Socket operation on non-socket

-89 is: Destination address required

-90 is: Message too long

-91 is: Protocol wrong type for socket

-92 is: Protocol not available

-93 is: Protocol not supported

-94 is: Socket type not supported

-95 is: Operation not supported

-96 is: Protocol family not supported

-97 is: Address family not supported by protocol

-98 is: Address already in use

-99 is: Cannot assign requested address

-100 is: Network is down

-101 is: Network is unreachable

-102 is: Network dropped connection on reset

-103 is: Software caused connection abort

-104 is: Connection reset by peer

-105 is: No buffer space available

-106 is: Transport endpoint is already connected

-107 is: Transport endpoint is not connected

-108 is: Cannot send after transport endpoint shutdown

-109 is: Too many references: cannot splice

-110 is: Connection timed out

-111 is: Connection refused

-112 is: Host is down

-113 is: No route to host

-114 is: Operation already in progress

-115 is: Operation now in progress

-116 is: Stale NFS file handle

-117 is: Structure needs cleaning

-118 is: Not a XENIX named type file

-119 is: No XENIX semaphores available

-120 is: Is a named type file

-121 is: Remote I/O error

-122 is: Disk quota exceeded

-123 is: No medium found

-124 is: Wrong medium type

-125 is: Operation canceled

-126 is: Required key not available

-127 is: Key has expired

-128 is: Key has been revoked

-129 is: Key was rejected by service

-130 is: Owner died

-131 is: State not recoverable

-132 is: Unknown error 132

132-255□□Unknown error

□□ (□□)